



## American Wheat Beer

Wheat malt and select hops create the recipe for this easy-drinking summertime classic. Light-bodied with a smooth finish, our Wheat Beer features an authentic dry wheat yeast.

IBUs: 18 - 22

OG: 1.041 - 1.045

FG: 1.012 - 1.016

ABV: 3.8% - 4.3%

Difficulty: Easy

Color: Deep Gold

### Contents

- Ingredients
- Grain Bag
- Hops may vary due to availability.
- Priming Sugar
- Bottle Caps
- Brewing Procedures

### Glossary

<b>OG</b> Original Gravity	<b>DME</b> Dried Malt Extract
<b>SG</b> Specific Gravity	<b>LME</b> Liquid Malt Extract
<b>FG</b> Final Gravity	<b>IBU</b> International Bittering Units ( <i>Tinseth</i> )
<b>CO<sub>2</sub></b> Carbon Dioxide	<b>ABV</b> Alcohol by Volume

### Ingredients

FERMENTABLES  
1 lb. Wheat DME  
SPECIALTY GRAINS  
4 oz. Caramel 8L  
HOPS  
2 packs of 3g Cluster Hops  
YEAST  
1 Sachet  
(NOTE: you will only use 1 teaspoon of the provided yeast sachet.)

## Recommended Procedures

### BREW DAY (DATE \_\_\_ / \_\_\_ / \_\_\_)

#### 1. READ

Read all of the recommended procedures before you begin.

#### 2. SANITIZE

Thoroughly clean and sanitize ALL brewing equipment and utensils that will come in contact with any ingredients, wort or beer with a certified sanitizer, e.g., Star San or IO Star.

#### 3. STEEP GRAINS

Pour 1.5 gallons of clean water into your brew pot and begin to heat. Pour crushed grains into grain bag and tie a loose knot at the top of the bag<sup>1</sup>. When the water is within an appropriate steeping temperature (150° - 165°F) place the grain bag into the brew pot<sup>2</sup>. Steep grains for approximately 20 minutes. Remove grain bag and without squeezing, allow liquid to drain back into brew pot. Your water is now wort.

#### 4. START BOIL

Bring your wort to a gentle, rolling boil. Add **all of the included DME** to the boiling wort. Continuously stir the DME into the wort as it returns to a gentle, rolling boil<sup>3</sup>.

#### 5. FOLLOW SCHEDULE<sup>4</sup>

As directed on the BREW DAY SCHEDULE (right), slowly sprinkle the first hop addition into the boiling wort (#1 in brew day schedule). Be careful not to let the wort boil over the pot. Using the provided BREW DAY SCHEDULE, note the time that each hop addition was added to the boil in order to keep your hop additions on schedule. Continue the gentle, rolling boil and follow the BREW DAY SCHEDULE until the boil is complete.

## Recommended Brew Day Equipment

- 8 Quart or Larger Brew Pot
- 1 Gallon Glass Fermenter
- Screw Cap with Hole
- Airlock
- Spoon or Paddle
- Hydrometer
- Thermometer
- No-Rinse Sanitizer
- Cleanser

### Brew Tips

<sup>1</sup>The grains should not be compacted inside the bag. Grains should steep loosely allowing the hot water to soak into all of the grain evenly.

<sup>2</sup>Pay careful attention not to let your steeping water exceed 170°F which leeches tannins into the wort.

<sup>3</sup>Pay careful attention that the DME does not accumulate and caramelize on the bottom of your brew pot.

<sup>4</sup>When consumed, hops can cause malignant hyperthermia in dogs, sometimes with fatal results. Even small amounts, including "spent" hops from brewing, can trigger a deadly reaction.

## BREW DAY SCHEDULE

1. Add 3 grams Cluster hops \_\_\_\_\_ : \_\_\_\_ (time)
2. Boil 40 minutes
3. Add other 3 grams Cluster hops \_\_\_\_\_ : \_\_\_\_ (time)
4. Boil final 20 minutes
5. Terminate boil \_\_\_\_\_ : \_\_\_\_ (time)

**Total Boil Time: 60 Minutes**

**Continue to Step #6**



## Recommended Procedures (continued)

### 6. COOL WORT & TRANSFER

Cool the wort down to approximately 70°F by placing the brew pot in a sink filled with ice water<sup>5</sup>. Siphon wort into a sanitized 1 gallon glass fermenter. Avoid transferring the heavy sediment (trub) from the brew pot to the fermenter. Be sure **not** to fill the glass fermenter past the "ONE GALLON" raised lettering on the jug. Take an OG reading with a sanitized hydrometer and record it in your ABV% CALCULATOR (right).

### 7. PITCH YEAST

Measure out **1 teaspoon** of yeast and pour the teaspoon into the glass fermenter (DO NOT REHYDRATE) and stir well with small end of a sanitized spoon or paddle. Firmly secure the screw cap onto the fermenter. Fill your airlock halfway with water and gently twist the airlock into the screw cap<sup>6</sup>. Move fermenter to a dark, warm, temperature-stable area (approx. 64° - 72°F). Remaining yeast can be refrigerated and stored for future use or discarded.

## FERMENTATION

### 8. MONITOR & RECORD

The wort will begin to ferment within 24 hours and you will notice CO2 releasing (bubbling) out of the airlock. Within 4 - 6 days the bubbling will slow down and become intermittent or may stop completely. When fermentation is complete (after 10 - 14 days and no bubbles for 48 hours) take a FG reading with a sanitized hydrometer and record it in your ABV% CALCULATOR (right).

### BOTTLING DAY (DATE \_\_\_ / \_\_\_ / \_\_\_)

### 9. READ

Read all of the recommended procedures before you begin.

### 10. SANITIZE

Thoroughly clean and sanitize ALL brewing equipment, utensils, and bottles that will come in contact with any ingredients, wort or beer with a certified sanitizer, e.g., Star San or IO Star.

### 11. PREPARE PRIMING SUGAR

In a small saucepan dissolve 1 oz. of priming sugar into 1/2 cup of boiling water for 5 minutes. Pour this mixture into a clean and sanitized 2 gallon bucket. Carefully siphon beer from the fermenter into the 2 gallon bucket. Avoid transferring any sediment. Stir gently for about a minute.

### 12. BOTTLE

Using your siphon setup and bottling wand, fill the bottles<sup>7</sup> to within approximately one inch of the top of the bottle. Use a bottle capper to apply sanitized crown caps.

### 13. BOTTLE CONDITION

Move the bottles to a dark, warm, temperature-stable area (approx. 64° - 72°F). Over the next two weeks the bottles will naturally carbonate. Carbonation times vary depending on the temperature and beer style, so be patient if it takes a week or so longer.

**CHILL & ENJOY YOUR TASTY BREW AND THANK YOU FOR  
CHOOSING BREWER'S BEST® PRODUCTS.**

## Brew Tips

<sup>5</sup>To avoid bacteria growth do this as rapidly as possible. Do not add ice directly to the wort. Alternatively, you can use a brewing accessory like a Wort Chiller.

<sup>6</sup>During fermentation if foam starts to push up into the airlock, slowly remove the airlock and replace it with a 2 foot section of 5/16" tubing. Place one end into the hole of the screw cap and the other into a bowl of sanitizer solution. This is known as a "Blow-off" set-up. Brewer's Best® recommends using this method when fermenting high gravity beers.

<sup>7</sup>Use standard crown bottles, preferably amber color. Make sure bottles are thoroughly clean. Use a bottle brush if necessary to remove stubborn deposits. Bottles should be sanitized prior to filling.

## Recommended Bottling Day Equipment

- 2 Gallon Bucket
- Siphon Setup
- Bottle Filling Wand
- 12 oz. Bottles (approx. 10)
- Brewer's Best® Crown Caps
- Bottle Brush
- Capper
- Sanitizer

## ABV% Calculator

$$(OG - FG) \times 131.25 = ABV\%$$

$$(\text{___}^* - \text{___}^{**}) \times 131.25 = \text{___}\%$$

\*OG from Step #6

\*\*FG from Step #8



*Brewer's Best is a registered trademark of the LD Carlson Co.*